

ORGANIC CHEMISTRY: PURIFICATION TECHNIQUES

Mastering Distillation

A diagnostic guide to isolating organic compounds—from simple separation to advanced fractional and pressure-manipulated techniques.


THE CORE PRINCIPLE

Vaporize. Condense. Isolate.

Distillation is the fundamental process of heating a liquid to create vapor, and then cooling that vapor to collect the purified liquid. It exploits differences in volatility.

The Two-Step Mechanism

1. **Vaporization:** Heat applied to the mixture turns the more volatile component into a gas.
2. **Condensation:** The gas travels through a cooled condenser, returning to a liquid state in a separate receiver.



Simple Distillation

The standard approach for separating volatile liquids from non-volatile impurities, or liquids with significantly different boiling points.

When to Use

When the boiling points of the two liquids differ by a wide margin (typically $>40\text{K}$). The liquids must be thermally stable and not decompose at their boiling points.

How it Works

The mixture is heated. The liquid with the lower boiling point vaporizes first, condenses, and is collected cleanly before the second liquid begins to boil.

Classic Example

Separating Chloroform (b.p. 334 K) and Aniline (b.p. 457 K).

$$\Delta \text{ b.p.} = 123 \text{ K}$$



You've Learned the Theory. Let's Test Them Now.

$$E=mc^2$$



Turn theory into marks with **unlimited MCQs, smart analysis, and focused revision.**

Practice Now



At prep.topall.app

Key Highlights

- » Free Study Material, Videos & Infographics
- » Push Your Limits with Level-Based Challenges
- » Climb the Leaderboard Among Fellow Aspirants
- » Practice Unlimited MCQs for NEET & JEE
- » Get Clear Explanations, Not Just Marks
- » Track Your Performance Smarter



METHOD 02


Fractional Distillation

Required when the boiling points of two liquids are too close for simple distillation to be effective.

- **The Challenge:** Vapors of liquids with close boiling points mix, preventing pure isolation.
- **The Solution:** A fractionating column is fitted between the flask and condenser.
- **The Mechanism:** The column provides many surfaces for heat exchange. Vapors condense and re-evaporate multiple times.
- **Theoretical Plates:** Each condensation/evaporation cycle is a 'plate'. Vapors of the low-boiling component reach the top first.

Industrial Application

Used universally in the petroleum industry to separate crude oil into distinct hydrocarbon fractions.



METHOD 03

Distillation Under Reduced Pressure

Also known as Vacuum Distillation. Designed specifically for liquids that are highly sensitive to heat.

The Golden Rule of Boiling

A liquid boils when its vapor pressure equals the external atmospheric pressure.

By using a **Vacuum Pump** to lower the external pressure, the liquid boils at a much lower temperature—safely below its decomposition point.

Textbook Example

Isolating Glycerol from spent-lye in the soap industry. (Glycerol normally decomposes before reaching its extremely high natural boiling point).

METHOD 04

Steam Distillation

An ingenious method for separating substances that are steam volatile but completely immiscible with water.

The Process

Steam is passed through a heated flask containing the mixture. The mixture of organic vapor and steam travels to the condenser, then separates into two distinct liquid layers in the receiver.

Classic Example: Separating Aniline from an aniline-water mixture.



The Chemistry

Exam Focus

$$P_{\text{(total)}} = p_1(\text{organic}) + p_2(\text{water})$$

Because $P_{\text{(total)}}$ reaches atmospheric pressure faster than p_1 alone, the organic liquid boils at a lower temperature than its normal boiling point.

The Distillation Diagnostic Matrix

How to select the correct purification technique based on chemical properties.

Technique	Boiling Point Diff (ΔT)	Special Condition	Classic Example
Simple	Wide ($>40K$)	Thermally stable	Chloroform + Aniline
Fractional	Narrow / Close	Thermally stable	Crude Oil fractions
Reduced Pressure	N/A (Usually High)	Decomposes at normal b.p.	Glycerol from spent-lye
Steam	N/A	Steam volatile, water-immiscible	Aniline + Water

Key Takeaways

1

Temperature dictates setup.

If liquids have vastly different boiling points, Simple Distillation works. If they are close, Fractional Distillation is mandatory to provide multiple theoretical plates.

2

Pressure manipulates heat.

Vacuum (Reduced Pressure) Distillation saves heat-sensitive compounds by lowering the external pressure, allowing boiling before decomposition occurs.

3

Immiscibility has advantages.

Steam Distillation utilizes the combined vapor pressures of water and an immiscible organic compound to achieve boiling at lower, safer temperatures.



You've Learned the Theory.

Now Let's Test It.

Reading notes gets you knowledge.

Practicing MCQs gets you marks.

That's exactly what TopAll Pro is built for.

Try TopAll Pro Now

What TopAll Pro Does Differently

-  **Stuck? Snap it. Solve it. — Doubts AI**
Photo → step-by-step solution in seconds, 24/7
-  **Your AI Coach finds your blind spots**
Concept-level weakness detection — not just chapter-level
-  **4.5 Lakh+ questions. Never run out.**
13× more content than any other prep app in India
-  **Build your own test in 60 seconds**
Pick a chapter, set difficulty — AI does the rest instantly.
-  **AI Recommendation that helps you improve**
AI Recommendation Analysis your Tests and tell you where you need to improve.



Practice the moment you finish studying
Jump in while the concept is still fresh in your head

4.5L+
MCQs

1.5L+
Students

AI Powered
In-Depth Analysis